

#### **SNS COLLEGE OF TECHNOLOGY** Coimbatore-35 An Autonomous Institution



Accredited by NBA – AICTE and Accredited by NAAC – UGC with 'A++' Grade Approved by AICTE, New Delhi & Affiliated to Anna University, Chennai

#### **DEPARTMENT OF ELECTRONICS & COMMUNICATION ENGINEERING**

#### **19ECT301- COMMUNICATION NETWORKS**

III YEAR/ V SEMESTER

#### UNIT 2 – DATA-LINK LAYER & NETWORK LAYER

**TOPIC 2– DLC SERVICES** 

DLC SERVICES/19ECT301 COMMUNICATION NETWORKS /E.CHRISTINA DALLY/AP/ECE/SNSCT







2

## our goals:

- understand principles behind link layer
   services:
  - error detection, correction
  - sharing a broadcast channel: multiple access
  - link layer addressing
  - Iocal area networks: Ethernet, VLANs
- instantiation, implementation of various link layer technologies







- introduction, services
- error detection, correction
- multiple access protocols
- LANs
  - addressing, ARP
  - Ethernet
  - switches
  - VLANS



# Link layer: Introduction




4

### terminology:

- hosts and routers: nodes
- communication channels that connect adjacent nodes along communication path: links
  - wired links
  - wireless links
  - LANs
- layer-2 packet: frame, encapsulates datagram

data-link layer has responsibility of transferring datagram from one node to physically adjacent node over a link





# Link layer: context



datagram transferred by different link protocols over different links:

 e.g., Ethernet on first link, frame relay on intermediate links, 802.11 on last link

# Each link protocol provides different services

 e.g., may or may not provide rdt over link

#### transportation analogy:

- trip from Princeton to Lausanne
  - limo: Princeton to JFK
  - plane: JFK to Geneva
  - train: Geneva to Lausanne
- tourist = datagram
- transport segment = communication link
- transportation mode = link layer protocol
- travel agent = routing algorithm



# Link layer services



- framing, link access:
  - encapsulate datagram into frame, adding header, trailer
  - channel access if shared medium
  - "MAC" addresses used in frame headers to identify source, dest
    - different from IP address!
- reliable delivery between adjacent nodes
  - we learned how to do this already (chapter 3)!
  - seldom used on low bit-error link (fiber, some twisted pair)
  - wireless links: high error rates
    - Q: why both link-level and end-end reliability?
      - A: correcting errors locally, rather than end-end



#### flow control:

pacing between adjacent sending and receiving nodes

#### error detection:

- errors caused by signal attenuation, noise.
- receiver detects presence of errors:
  - signals sender for retransmission or drops frame

#### error correction:


 receiver identifies and corrects bit error(s) without resorting to retransmission

#### half-duplex and full-duplex


 with half duplex, nodes at both ends of link can transmit, but not at same time



- in each and every host
- link layer implemented in "adaptor" (aka network interface card NIC) or on a chip
  - Ethernet card, 802.11 card; Ethernet chipset
  - implements link, physical layer
- attaches into host's system buses
- combination of hardware, software, firmware



8



- sending side:
  - encapsulates datagram in frame
  - adds error checking bits, rdt, flow control, etc.

receiving side

- looks for errors, rdt, flow control, etc
- extracts datagram, passes to upper layer at receiving side



# Link layer, LANs: outline



10

- introduction, services
- error detection, correction
- multiple access protocols
- LANs
  - addressing, ARP
  - Ethernet
  - switches
  - VLANS




# **Error detection**



EDC= Error Detection and Correction bits (redundancy)

- D = Data protected by error checking, may include header fields
- Error detection not 100% reliable!
  - protocol may miss some errors, but rarely
  - larger EDC field yields better detection and correction






# Parity checking




#### single bit parity:


*d*etect single bit errors



## two-dimensional bit parity:

detect and correct single bit errors





\*\*\*

# Internet checksum (review)



**goal:** detect "errors" (e.g., flipped bits) in transmitted packet (note: used at transport layer *only*)

#### sender:

- treat segment contents as sequence of 16-bit integers
- checksum: addition (1's complement sum) of segment contents
- sender puts checksum value into UDP checksum field

#### receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
  - NO error detected
  - YES no error detected. But maybe errors nonetheless?

# Cyclic redundancy check



- more powerful error-detection coding
- view data bits, D, as a binary number
- choose r+l bit pattern (generator), G
- ✤ goal: choose r CRC bits, R, such that
  - <D,R> exactly divisible by G (modulo 2)
  - receiver knows G, divides <D,R> by G. If non-zero remainder: error detected!
  - can detect all burst errors less than r+1 bits
- widely used in practice (Ethernet, 802.11 WiFi, ATM)

$$\begin{array}{c} \longleftarrow & d \text{ bits } \longrightarrow & \leftarrow \text{ r bits } \longrightarrow & & bit \\ \hline D: \text{ data bits to be sent } R: CRC \text{ bits } & pattern \\ & D * 2^{r} XOR R & & mathematical \\ & formula \end{array}$$







#### want: $D \cdot 2^r XOR R = nG$ equivalently: $D \cdot 2^r = nG XOR R$ equivalently:

if we divide D<sup>.</sup>2<sup>r</sup> by G, want remainder R to satisfy:

$$R = remainder[\frac{D \cdot 2^r}{G}]$$

101011 1001  $\cap \cap \cap$ 10 011001 110 Modulo-2 arithmetic without carries in 000 addition or **borrows** in 1100 subtraction 1001 1010 1001





- introduction, services
- error detection, correction
- multiple access protocols
- LANs
  - addressing, ARP
  - Ethernet
  - switches
  - VLANS

# Multiple access links, protocols


## two types of "links":

#### \* point-to-point

- PPP for dial-up access
- point-to-point link between Ethernet switch, host

#### broadcast (shared wire or medium)

- old-fashioned Ethernet
- upstream HFC
- 802.11 wireless LAN



7





- single shared broadcast channel
- two or more simultaneous transmissions by nodes: interference
  - collision if node receives two or more signals at the same time

#### multiple access protocol

- distributed algorithm that determines how nodes share channel, i.e., determine when node can transmit
- communication about channel sharing must use channel itself!
  - no out-of-band channel for coordination



## An ideal multiple access protocol



# *Given:* broadcast channel of rate R bps *Desired data:*

- I. when one node wants to transmit, it can send at rate R.
- 2. when M nodes want to transmit, each can send at average rate R/M
- 3. fully decentralized:
  - no special node to coordinate transmissions
  - no synchronization of clocks, slots
- 4. Simple

#### MAC: Media Access Control





20

#### three broad classes:

#### channel partitioning

- divide channel into smaller "pieces" (time slots, frequency, code)
- allocate piece to node for exclusive use

#### random access

- channel not divided, allow collisions
- "recover" from collisions


## "taking turns"

 nodes take turns, but nodes with more to send can take longer turns Channel partitioning MAC protocols: TDMA



## TDMA: time division multiple access

- access to channel in "rounds"
- each station gets fixed length slot (length = pkt trans time) in each round
- unused slots go idle
- example: 6-station LAN, 1,3,4 have pkt, slots
   2,5,6 idle



DLC SERVICES/19ECT301 COMMUNICATION NETWORKS /E.CHRISTINA DALLY/AP/ECE/SNSCT




#### Channel partitioning MAC protocols: FDMA



22

### FDMA: frequency division multiple access

- channel spectrum divided into frequency bands
- each station assigned fixed frequency band
- unused transmission time in frequency bands go idle
- example: 6-station LAN, 1,3,4 have pkt, frequency bands 2,5,6 idle



# Random access protocols



- when node has packet to send
  - transmit at full channel data rate R.
  - no a priori coordination among nodes
- \* two or more transmitting nodes  $\rightarrow$  "collision",
- \* random access MAC protocol specifies:
  - how to detect collisions
  - how to recover from collisions (e.g., via delayed retransmissions)
- examples of random access MAC protocols:
  - slotted ALOHA
  - ALOHA
  - CSMA, CSMA/CD, CSMA/CA



# Slotted ALOHA




#### assumptions:

- \* all frames same size
- time divided into equal size slots (time to transmit I frame)
- nodes start to transmit only slot beginning
- nodes are synchronized
- if 2 or more nodes transmit in slot, all nodes detect collision

#### operation:

- when node obtains fresh
   frame, transmits in next slot
  - if no collision: node can send new frame in next slot
  - if collision: node retransmits frame in each subsequent slot with prob. p until success



#### Pros:

- single active node can continuously transmit at full rate of channel
- highly decentralized: only slots in nodes need to be in sync
- simple

#### collisions, wasting slots

idle slots

Cons:

- nodes may be able to detect collision in less than time to transmit packet
- clock synchronization



# Slotted ALOHA: efficiency



efficiency: long-run fraction of successful slots (many nodes, all with many frames to send)

- suppose: N nodes with many frames to send, each transmits in slot with probability p
- prob that given node has success in a slot = p(1p)<sup>N-1</sup>
- ✤ prob that any node has a success = Np(1-p)<sup>N-1</sup>

- max efficiency: find p\* that maximizes Np(I-p)<sup>N-I</sup>
- for many nodes, take limit of Np\*(1-p\*)<sup>N-1</sup> as N goes to infinity, gives:


max efficiency = 1/e = .37

*at best:* channel used for useful transmissions 37% of time!





- unslotted Aloha: simpler, no synchronization
- when frame first arrives
  - transmit immediately
- collision probability increases:
  - frame sent at t<sub>0</sub> collides with other frames sent in [t<sub>0</sub>l,t<sub>0</sub>+l]







P(success by given node) = P(node transmits).

P(no other node transmits in  $[t_0-1,t_0]$  · P(no other node transmits in  $[t_0-1,t_0]$ 

= 
$$p \cdot (1-p)^{N-1} \cdot (1-p)^{N-1}$$
  
=  $p \cdot (1-p)^{2(N-1)}$ 

... choosing optimum p and then letting n  $\longrightarrow \infty$ 

= I/(2e) = .18

#### even worse than slotted Aloha!



## CSMA (carrier sense multiple access)



CSMA: listen before transmit:
if channel sensed idle: transmit entire frame
 if channel sensed busy, defer transmission

human analogy: don't interrupt others!




# **CSMA** collisions



80

#### spatial layout of nodes

- collisions can still occur: propagation delay means two nodes may not hear each other's transmission
- collision: entire packet transmission time wasted
  - distance & propagation delay play role in in determining collision probability



# CSMA/CD (collision detection)



## CSMA/CD: carrier sensing, deferral as in CSMA

- collisions <u>detected</u> within short time
- colliding transmissions aborted, reducing channel wastage

#### collision detection:


- easy in wired LANs: measure signal strengths, compare transmitted, received signals
- difficult in wireless LANs: received signal strength overwhelmed by local transmission strength
- human analogy: the polite conversationalist





**3**2

spatial layout of nodes





## Ethernet CSMA/CD algorithm



- I. NIC receives datagram from network layer, creates frame
- 2. If NIC senses channel idle, starts frame transmission. If NIC senses channel busy, waits until channel idle, then transmits.
- 3. If NIC transmits entire frame without detecting another transmission, NIC is done with frame !

- 4. If NIC detects another transmission while transmitting, aborts and sends jam signal
- 5. After aborting, NIC enters binary (exponential) backoff:
  - after m<sup>th</sup> collision, NIC chooses K at random from {0,1,2, ..., 2<sup>m</sup>-1}. NIC waits K<sup>5</sup>12 bit times, returns to Step 2
  - longer backoff interval with more collisions





T<sub>prop</sub> = max prop delay between 2 nodes in LAN

t<sub>trans</sub> = time to transmit max-size frame

$$efficiency = \frac{1}{1 + 5t_{prop}/t_{trans}}$$

- efficiency goes to I
  - as t<sub>prop</sub> goes to 0
  - as t<sub>trans</sub> goes to infinity
- better performance than ALOHA: and simple, cheap, decentralized!

# "Taking turns" MAC protocols



### channel partitioning MAC protocols:


- share channel efficiently and fairly at high load
- inefficient at low load: delay in channel access, I/N bandwidth allocated even if only I active node!

### random access MAC protocols

- efficient at low load: single node can fully utilize channel
- high load: collision overhead
- "taking turns" protocols look for best of both worlds!

## polling:

- master node "invites" slave nodes to transmit in turn
- typically used with
   "dumb" slave devices
- concerns:
  - polling overhead
  - latency
  - single point of failure (master)



"Taking turns" MAC protocols



36




#### 37

## token passing:


 control token passed from one node to next sequentially.

"Taking turns" MAC protocols


- token message
- concerns:
  - token overhead
  - latency
  - single point of failure (token)







- multiple 40Mbps downstream (broadcast) channels
  - single CMTS transmits into channels
- multiple 30 Mbps upstream channels
  - multiple access: all users contend for certain upstream channel time slots (others assigned)



#### **DOCSIS**: data over cable service interface spec

- FDM over upstream, downstream frequency channels
- TDM upstream: some slots assigned, some have contention
  - downstream MAP (bandwidth allocation map) frame: assigns upstream slots
  - request for upstream slots (and data) transmitted random access (binary backoff) in selected slots

39



## Summary of MAC protocols



40

- channel partitioning, by time, frequency or code
  - Time Division, Frequency Division
- random access (dynamic),
  - ALOHA, S-ALOHA, CSMA, CSMA/CD
  - carrier sensing: easy in some technologies (wire), hard in others (wireless)
  - CSMA/CD used in Ethernet
  - CSMA/CA used in 802.11 (Collision Avoidance)
- taking turns
  - polling from central site, token passing
  - bluetooth, FDDI, token ring





<mark>4</mark>1

#### **THANK YOU**

DLC SERVICES/19ECT301 COMMUNICATION NETWORKS /E.CHRISTINA DALLY/AP/ECE/SNSCT